



Read Me • Lisez-moi • Bitte lesen • Leggimi • Viktigt • Léame • Lees mij • お読みください

FileMaker Pro 7.0v3a Updater

7/15/2005

Software description

This software updates the Windows version of FileMaker Pro 7.0v3 to version 7.0v3a. This update will improve performance when displaying popup lists.

Note: This software only updates the Windows version of FileMaker Pro 7.0v3. **If you have an earlier version of FileMaker Pro 7, please update it to 7.0v3 prior to running this software.** This software will not update FileMaker Developer 7.

Installation instructions

To ensure a smooth installation, disable virus detection software before applying the update, and re-enable it after you are finished.

Note: You may be prompted to insert your original installation CD or locate the original installation software during the update process.

1. Quit FileMaker Pro 7. Other applications can remain open.
2. Double-click the FileMaker 7.0v3a updater program.
3. Click **Next** to display the license agreement.
4. Read and accept the displayed license agreement, then click **Update** to update your software.
5. After the update has completed, you should see a message confirming the successful installation of the new version.
6. Click **Finish** to quit the updater when completed.

Once the update has completed successfully, the file version of the FileMaker Pro.exe will change from **7.0.3.320** to **7.0.3.321**. By default, the FileMaker Pro.exe will be installed in c:\Program Files\FileMaker\FileMaker Pro 7 folder. Other version information such as the Product Version or the version number in the About FileMaker Pro dialog box will not be changed by this updater.

If the update does not complete successfully, try reinstalling the previous version of FileMaker 7 using your original installation program and running the updater again by doing the following:

1. Create backup copies of any files you saved in the FileMaker Pro 7 application folder.
2. Use the Add/Remove Programs control panel to remove FileMaker Pro 7.
3. Install FileMaker Pro 7 using your original installation program.
4. Update FileMaker Pro 7 to v3 using the FileMaker v3 updater.
5. At this point, you can run the FileMaker Pro 7.0v3a updater program again.

If, after following the steps above, you are still unable to successfully update to FileMaker Pro 7.0v3a, please contact FileMaker Technical Support for assistance.

Silent Install Instructions

Performing a silent install is a one-step process. The following is the basic syntax of the command that needs to be entered at the Command Prompt:

c:\>FileMaker Pro 7v3a update.exe /V"/q"

The full set of silent install options are:

Option	Parameters	Meaning
/q	n b r f	<p>Sets user interface level.</p> <p>q , qn - No UI</p> <p>qb - Basic UI. Use qb! to hide the Cancel button.</p> <p>qr - Reduced UI with no dialog box displayed at the end of the installation.</p> <p>qf - Full UI and any authored FatalError, UserExit or Exit dialog boxes at the end.</p> <p>qn+ - No UI except for a dialog box displayed at the end.</p> <p>qb+ - Basic UI with a dialog box displayed at the end. The dialog box is not displayed if the user cancels the installation. Use qb+! or qb!+ to hide the Cancel button.</p> <p>qb- - Basic UI with no modal dialog boxes. Please note that /qb+- is not a supported UI level. Use qb-! or qb!- to hide the Cancel button.</p> <p>Note that the ! option is available with Windows Installer version 2.0 and works only with basic UI. It is not valid with full UI.</p>